



# **Jumps and Branches**

## **ICS312 Machine-Level and Systems Programming**

Henri Casanova ([henric@hawaii.edu](mailto:henric@hawaii.edu))

# Modifying Instruction Flow

- So far we have seen instructions to
  - Move data back and forth between memory and registers
  - Do some data conversion
  - Perform arithmetic operation on that data
- Now we're going to learn about instructions that modify the order in which instructions are executed
  - i.e., we not always execute the next instruction
- High-level programming languages provide control structures
  - for loops, while loop, if-then-else statements, etc.
- Assembly language basically provides a **goto**
  - An infamous instruction, that causes “spaghetti code”

# The JMP Instruction

- JMP allows you to “jump” to a **code label**
- Example:

...

```
add eax, ebx
```

```
jmp here
```

```
sub al, bl
```

```
movsx ax, al
```

These instructions will never be executed!



**here:**

```
call print_int
```

...

# The JMP Instruction

- The ability to jump to a **label** in the assembly code is convenient
- In machine code there is no such thing as a label: only addresses
- So one would constantly have to compute addresses by hand
  - e.g., “jump to the instruction +4319 bytes from here in the source code”
  - e.g., “jump to the instruction -18 bytes from here in the source code”
  - This is what programmers, way back when, used to do by hand, using **signed displacements in bytes**
  - The displacements are added to the EIP register (program counter)
- There are three versions of the JMP instruction in machine code:
  - **Short jump**: Can only jump to an instruction that is within 128 bytes in memory of the jump instruction (1-byte displacement)
  - **Near jump**: 4-byte displacement (any location in the code segment)
  - **Far jump**: very rare jump to another code segment
    - We won't use this at all

# The JMP Instruction

- A **short jump**:

jmp label

or jmp short label

- A **near jump**:

jmp near label

- Why do we even have this?

- Remember that instructions are encoded in binary
- To jump one needs to encode the number of bytes to add/subtract to the program counter
- If this number is large, we need many bits to encode it
- If this number is small, we want to use few bits so that our program takes less space in memory
  - i.e., the encoding of a short jmp instruction takes fewer bits than the encoding of a near jmp instruction (3 bytes less)
- In a code that has 100,000 near jumps, if you can replace 50% of them by short jumps, you save ~150KB (in the size of the executable)

# Conditional Branches

- The JMP instruction is an **unconditional branch**
- We also have **conditional branch** instructions
- These instructions jump to an address in the code segment (i.e., a label) based on the content of the FLAGS register
- As a programmer you don't modify the FLAGS register, instead it is updated by
  - All instructions that perform arithmetic operations
  - The cmp instruction, which subtracts one operand from another but doesn't store the result anywhere

# Unsigned Integers

- When you use unsigned integers the bits in the FLAGS register (also called “flags”) that are important are:
  - ZF: The Zero Flag (set to 1 if result is 0)
  - CF: The Carry Flag
    - During an arithmetic operation, used to detect overflow or to do clever arithmetic since it may denote a carry or a borrow
- Consider: `cmp a, b` (which computes  $a-b$ )
  - If  $a = b$ : ZF is set, CF is not set
  - If  $a < b$ : ZF is not set, CF is set (borrow)
    - If you were computing the difference for real, this would mean an error!
  - If  $a > b$ : ZF is not set, CF is not set
- **Therefore, by looking at ZF and CF you can determine the result of the comparison!**
  - We’ll see how we “look” at the flags shortly

# Signed Integers

- For signed integers you should care about three flags:
  - ZF: zero flag
  - OF: overflow flag (set to 1 if the result overflows or underflows)
  - SF: sign flag (set to 1 if the result is negative)
- Consider: `cmp a, b` (which computes `a-b`)
  - If `a = b`: ZF is set, OF is not set, SF is not set
  - If `a < b`: ZF is not set, and `SF ≠ OF`
  - If `a > b`: ZF is not set, and `SF = OF`
- Therefore, by looking at ZF, SF, and OF you can determine the result of the comparison!



# Signed Integers: SF and OF???

- Why do we have this odd relationship between SF and OF?
- Consider two signed integers  $a$  and  $b$ , and remember that we compute  $(a-b)$
- If  $a < b$ 
  - If there is no overflow, then  $(a-b)$  is a negative number!
  - If there is overflow, then  $(a-b)$  is (erroneously) a positive number
  - Therefore, in both cases  $SF \neq OF$
- If  $a > b$ 
  - If there is no overflow, the (correct) result is positive
  - If there is an overflow, the (incorrect) result is negative
  - Therefore, in both cases  $SF = OF$

# Signed Integers: SF and OF???

- Example:  $a = 80h$  (-128d),  $b = 23h$  (+35d) ( $a < b$ )
  - $a - b = a + (-b) = 80h + DDh = 15Dh$
  - dropping the 1, we get  $5Dh$  (+93d), which is erroneously positive!
  - So, SF=0 and OF=1
- Example:  $a = F3h$  (-13d),  $b = 23h$  (+35d) ( $a < b$ )
  - $a - b = a + (-b) = F3h + DDh = D0h$  (-48d)
  - $D0h$  is negative and we have no overflow (in range)
  - So, SF=1 and OF=0
- Example:  $a = F3h$  (-13d),  $b = 82h$  (-126d) ( $a > b$ )
  - $a - b = a + (-b) = F3h + 7Eh = 171h$
  - dropping the 1, we get  $71h$  (+113d), which is positive and we have no overflow
  - So, SF=0 and OF=0
- Example:  $a = 70h$  (112d),  $b = D8h$  (-40d) ( $a > b$ )
  - $a - b = a + (-b) = 70h + 28h = 98h$ , which is erroneously negative
  - So, SF=1 and OF=1

# Summary

	cmp a,b	ZF	CF	OF	SF
unsigned	a==b	1	0		
	a<b	0	1		
	a>b	0	0		
signed	a==b	1		0	0
	a<b	0		v	!v
	a>b	0		v	v



# Simple Conditional Branches

- There is a large set of conditional branch instructions that act based on bits in the FLAGS register
- The simple ones just branch (or not) depending on the value of one of the flags:
  - ZF, OF, SF, CF, PF
  - PF: Parity Flag
    - Set to 0 if the number of bits set to 1 in the lower 8-bit of the “result” is odd, to 1 otherwise



# Simple Conditional Branches

- JZ** branches if ZF is set
- JNZ** branches if ZF is unset
- JO** branches if OF is set
- JNO** branches if OF is unset
- JS** branches if SF is set
- JNS** branches if SF is unset
- JC** branches if CF is set
- JNC** branches if CF is unset
- JP** branches if PF is set
- JNP** branches if PF is unset

# Example

- Consider the following C-like code with register-like variables

```
if (EAX == 0)
```

```
    EBX = 1;
```

```
else
```

```
    EBX = 2;
```

- Here it is in x86 assembly

```
    cmp    eax, 0           ; do the comparison
```

```
    jz     thenblock       ; if = 0, then goto thenblock
```

```
    mov    ebx, 2          ; else clause
```

```
    jmp    next            ; jump over the then clause
```

```
thenblock:
```

```
    mov    ebx, 1          ; then clause
```

```
next:
```

- Could use `jnz` and be the other way around

# Another Example

- Say we have the following C code (let us assume that EAX contains a value that we interpret as **signed**)

```
if (EAX >= 5)
```

```
    EBX = 1;
```

```
else
```

```
    EBX = 2;
```

- This is much less straightforward
- Let's go back to our table for signed numbers

	cmp a,b	ZF	OF	SF
signed	a=b	1	0	0
	a<b	0	v	!v
	a>b	0	v	v

After executing `cmp eax, 5`

if  $(OF = SF)$  then  $a \geq b$

# Another Example (continued)

- $a \geq b$  if (OF = SF)
- Skeleton program

```
cmp    eax, 5
```

Comparison

```
????
```

Testing relevant flags

```
thenblock:
```

```
    mov ebx, 1
```

```
    jmp end
```


“Then” block

```
elseblock:
```

```
    mov ebx, 2
```

“Else” block

```
end:
```





# Another Example (continued)

- $a \geq b$  if (OF = SF)
- Program:

```
        cmp     eax, 5           ; do the comparison
        jo     oset            ; if OF = 1 goto oset
        js     elseblock       ; (OF=0) and (SF = 1) goto elseblock
        jmp    thenblock       ; (OF=0) and (SF=0) goto thenblock
oset:
        jns    elseblock       ; (OF=1) and (SF = 0) goto elseblock
        jmp    thenblock       ; (OF=1) and (SF=1) goto thenblock
thenblock:
        mov    ebx, 1
        jmp    end
elseblock:
        mov    ebx, 2
end:
```

# Another Example (continued)

```
    cmp     eax, 5           ; do the comparison
    jo      oset            ; if OF = 1 goto oset
    js      elseblock       ; (OF=0) and (SF = 1) goto elseblock
    jmp     thenblock       ; (OF=0) and (SF=0) goto thenblock
```

oaset:

```
    jns     elseblock       ; (OF=1) and (SF = 0) goto elseblock
    jmp     thenblock       ; (OF=1) and (SF=1) goto thenblock
```

thenblock:

```
    mov ebx, 1
    jmp end
```

elseblock:

```
    mov ebx, 2
```

end:

Unneeded instruction, we can just "fall through"

The book has the same example, but their solution is the other way around



## **A bit too hard?**

- One can play tricks by putting the else block before the then block
  - See example in the book
- The previous two examples are really awkward, and it's very easy to introduce bugs
- Consequently, x86 assembly provides other branch instructions to make our life much easier :)
- Let's look at these instructions...

# More branches

cmp x, y			
signed		unsigned	
Instruction	branches if	Instruction	branches if
JE	$x = y$	JE	$x = y$
JNE	$x \neq y$	JNE	$x \neq y$
JL, JNGE	$x < y$	JB, JNAE	$x < y$
JLE, JNG	$x \leq y$	JBE, JNA	$x \leq y$
JG, JNLE	$x > y$	JA, JNBE	$x > y$
JGE, JNL	$x \geq y$	JAE, JNB	$x \geq y$

# Redoing our Example

```
if (EAX >= 5)
```

```
    EBX = 1;
```

```
else
```

```
    EBX = 2;
```

```
    cmp    eax, 5
```

```
    jge   thenblock
```

```
    mov    ebx, 2
```

```
    jmp   end
```

```
thenblock:
```

```
    mov    ebx, 1
```

```
end:
```



# The **FLAGS** register

- Is it very important to remember that many instructions change the bits of the **FLAGS** register
- So you should “act” on flag values immediately, and not expect them to remain unchanged inside **FLAGS**
  - or you can save them by-hand for later use perhaps



# Conclusion

- In the next set of lecture notes we'll see how to translate high-level control structures (if-then-else, while, for, etc.) into assembly based on what we just described
  - We've basically seen if-the-else already